



- MIRxxxE



* **Software Release Note**

Setup MEQ E Series v0.2.2.exe

Apply to Firmware version ≥ 2.6

- Changed mute buttons color from “Orange” to “Red”
- Added channel name on the “Level” and “Channel” pages
- Changed the color of the plot traces
- Increased plot resolution from 2.9Hz to 0.7Hz
- Added delay adjustment by mouse dragging
- Added advanced channel link group
- Added latency link group
- Improved groups management, now working both in Off-line and On-line mode
- Added groups unique identifier
- Added “Read/Load current group settings from/to device” options on the connect device window
- Improved “Loudness Filter” process: added filter frequency and Max/Min threshold editing
- Added “LINEAR PHASE EQ” mode on input
- Fixed the file browse issue: now it remembers the last folder path used

* **Firmware Release Note**

MIR-E Series v2.6.sfu

- Added “LINEAR PHASE EQ” mode on input
- Improved “Loudness Filter” process